

# Ac-DEVD-AFC \*CAS 201608-14-2\*

Catalog number: 13401 Unit size: 5 mg

Component	Storage	Amount
Ac-DEVD-AFC *CAS 201608-14-2*	Freeze (<-15 °C), Minimize light exposure	5 mg

# OVERVIEW

Ac-DEVD-AFC is a fluorogenic substrate for caspase 3, a protease that is rapidly activated when cells are exposed to apoptotic conditions and that cleaves poly(ADP-ribose) polymerase. The 7-amido-4-trifluoromethylcoumarin derivatives have better membrane permeability than the 7-amido-4-methylcoumarin derivatives.

#### AT A GLANCE

Important notes

It is important to store at <-15 °C and should be stored in cool, dark place.

It can be used within 12 months from the date of receipt.

#### SAMPLE EXPERIMENTAL PROTOCOL

Following protocol only provides a guideline, and should be modified according to your specific needs.

# General Solution Caspase Assays Using AMC, AFC, pNA, R110 and ProRed Substrates

- 1. Prepare a 10 mM stock solution in DMSO.
- 2. Prepare a 2X caspase substrate (50  $\mu$ M) assay solution as the following: 50  $\mu$ L substrate stock solution, 100  $\mu$ L DTT (1M), 400  $\mu$ L EDTA (100 mM), 10 mL Tris Buffer (20 mM), pH =7.4.
- 3. Mix equal volume of the caspase standards or samples with 2X caspase substrate assay solution, and incubate the solutions at room temperature for at least 1 hour.
- 4. Monitor the fluorescence using a fluorescence microplate reader, or absorbance using an absorbance microplate reader.

#### Cell Caspase Assays Using Cell-Permeable FMK Caspase Probes

- 1. Prepare a 2-5 mM stock solution in DMSO.
- 2. Treat cells as desired.
- 3. Prepare a 2X permeable caspase substrate (20  $\mu\text{M})$  assay solution by diluting the DMSO stock solution (from Step 2.1) in Hanks with 20 mM Hepes buffer (HHBS).
- Mix equal volume of the treated cells with 2X caspase substrate assay solution (from Step 2.3), and incubate the cells in a 37°C, 5% CO<sub>2</sub> incubator for at least1 hour.
- 5. Wash the cells with HHBS for at least once.
- 6. Monitor the fluorescence intensity by a flow cytometer, a fluorescence microscope or a fluorescence microplate reader.

# Cell Caspase Assays Using Cell-Permeable FMK Caspase Probes (For #13470-13476 only)

1. Prepare a 250X stock solution by adding 50  $\mu L$  DMSO into the vial.

### 2. Treat cells as desired.

- 3. Add 250 X DMSO stock solution into the cell solution at a 1:250 ratio (such as 2  $\mu L$  to 500  $\mu L$  cells), and incubate the cells in a 37°C, 5% CO2 incubator for 1 hour.
- 4. Wash the cells with HHBS for at least once.
- Monitor the fluorescence intensity by flow cytometer, fluorescence microscopy or fluorescent microplate reader.

### EXAMPLE DATA ANALYSIS AND FIGURES



Figure 1. Chemical structure for Ac-DEVD-AFC \*CAS 201608-14-2\*

## DISCLAIMER

AAT Bioquest provides high-quality reagents and materials for research use only. For proper handling of potentially hazardous chemicals, please consult the Safety Data Sheet (SDS) provided for the product. Chemical analysis and/or reverse engineering of any kit or its components is strictly prohibited without written permission from AAT Bioquest. Please call 408-733-1055 or email info@aatbio.com if you have any questions.